# ACS Shell Command Authorization Sets on IOS and ASA/PIX Configuration Example

Document ID: 99361

#### Introduction

#### **Prerequisites**

Requirements

Components Used

Conventions

#### **Command Authorization Sets**

#### Add a Shell Command Authorization Set

Scenario 1: Privilege for Read–Write Access or Full Access

Scenario 2: Privilege for Read-Only Access

Scenario 3: Privilege for Restricted Access

#### Associate the Shell Command Authorization Set to User Group

Associate the Shell Command Authorization Set (ReadWrite Access) to User Group (Admin Group)

Associate the Shell Command Authorization Set (ReadOnly Access) to User Group (Read-Only Group)

Associate the Shell Command Authorization Set (Restrict\_access) to User

**IOS Router Configuration** 

**ASA/PIX Configuration** 

**NetPro Discussion Forums – Featured Conversations** 

**Related Information** 

#### Introduction

This document describes how to configure the shell authorization sets in Cisco Secure Access Control Server (ACS) for AAA clients, such as IOS routers or switches and Cisco Security Appliances (ASA and PIX) with TACACS+ as the authorization protocol.

## **Prerequisites**

### Requirements

This document assumes that the basic configurations are set in both AAA Clients and ACS.

In ACS, choose **Interface Configuration > Advanced Options**, and ensure that the **Per–user TACACS+/RADIUS Attributes** check box is selected.

### **Components Used**

The information in this document is based on the Cisco Secure Access Control Server (ACS) that runs the software version 3.3 and later.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, make sure that you understand the potential impact of any command.

#### Conventions

Refer to the Cisco Technical Tips Conventions for more information on document conventions.

#### **Command Authorization Sets**

Command authorization sets provide a central mechanism to control the authorization of each command that is issued on any given network device. This feature greatly enhances the scalability and manageability required to set authorization restrictions.

In ACS, the default command authorization sets include Shell Command Authorization Sets and PIX Command Authorization Sets. Cisco device management applications, such as CiscoWorks Management Center for Firewalls, can instruct ACS to support additional command authorization set types.

**Note:** PIX Command Authorization Sets require that the TACACS+ command authorization request identify the service as *pixshell*. Verify that this service has been implemented in the version of PIX OS that your firewalls use; if not, use Shell Command Authorization Sets to perform command authorization for PIX devices. Refer to Configuring a Shell Command Authorization Set for a User Group for more information.

**Note:** As of PIX OS version 6.3, the pixshell service has not been implemented.

In order to offer more control of device—hosted administrative Telnet sessions, a network device that uses TACACS+ can request authorization for each command line before it executes. You can define a set of commands that are permitted or denied for execution by a particular user on a given device. ACS has further enhanced this capability with these features:

- Reusable Named Command Authorization Sets Without directly citing any user or user group, you can create a named set of command authorizations. You can define several command authorization sets that delineate different access profiles. For example:
  - ◆ A *Help desk* command authorization set could permit access to high–level browsing commands, such as **show run**, and deny any configuration commands.
  - ♦ An *All network engineers* command authorization set could contain a limited list of permitted commands for any network engineer in the enterprise.
  - ♦ A *Local network engineers* command authorization set could permit all commands (and include IP address configuration commands).
- Fine Configuration Granularity You can create associations between named command authorization sets and network device groups (NDGs). Thus, you can define different access profiles for users depending on which network devices they access. You can associate the same named command authorization set with more than one NDG and use it for more than one user group. ACS enforces data integrity. Named command authorization sets are kept in the ACS internal database. You can use the ACS Backup and Restore features to back up and restore them. You can also replicate command authorization sets to secondary ACSs along with other configuration data.

For command authorization set types that support Cisco device management applications, the benefits are similar when you use command authorization sets. You can apply command authorization sets to ACS groups that contain users of the device management application in order to enforce authorization of various privileges in a device management application. The ACS groups can correspond to different roles within the device management application, and you can apply different command authorization sets to each group, as applicable.

ACS has three sequential stages of command authorization filtering. Each command authorization request is evaluated in the order listed:

- 1. **Command Match** ACS determines whether the command that is processed matches a command listed in the command authorization set. If the command is not matched, command authorization is determined by the Unmatched Commands setting: *permit* or *deny*. Otherwise, if the command is matched, evaluation continues.
- 2. **Argument Match** ACS determines whether the command arguments presented match the command arguments listed in the command authorization set.
  - ◆ If any argument is not matched, command authorization is determined by whether the Permit Unmatched Args option is enabled. If unmatched arguments are permitted, the command is authorized and evaluation ends; otherwise, the command is not authorized and evaluation ends.
  - ♦ If all arguments are matched, evaluation continues.
- 3. **Argument Policy** Once ACS determines that the arguments in the command match arguments in the command authorization set, ACS determines whether each command argument is explicitly permitted. If all arguments are explicitly permitted, ACS grants command authorization. If any arguments is not permitted, ACS denies command authorization.

#### Add a Shell Command Authorization Set

This section includes these scenarios that describe how to add a command authorization set:

- Scenario 1: Privilege for Read–Write Access or Full Access
- Scenario 2: Privilege for Read-Only Access
- Scenario 3: Privilege for Restricted Access

**Note:** Refer to the Adding a Command Authorization Set section of the User Guide for Cisco Secure Access Control Server 4.1 for more information about how to create command authorization sets. Refer to Editing a Command Authorization Set and Deleting a Command Authorization Set for more information about how to edit and delete command authorization sets.


### Scenario 1: Privilege for Read-Write Access or Full Access

In this scenarios, users are granted read-write (or full) access.

In the Shell Command Authorization Set area of the Shared Profile Components window, configure these settings:

- 1. In the Name field, enter **ReadWriteAccess** as the command authorization set name.
- 2. In the Description field, enter a description for the command authorization set.
- 3. Click the **Permit** radio button, and then click **Submit**.

**Shared Profile Components** 



#### Scenario 2: Privilege for Read-Only Access

In this scenarios, users are able to use only **show** commands.


In the Shell Command Authorization Set area of the Shared Profile Components window, configure these settings:

- 1. In the Name field, enter **ReadOnlyAccess** as the name of the command authorization set.
- 2. In the Description field, enter a description for the command authorization set.
- 3. Click the **Deny** radio button.
- 4. Enter the **show** command in the field above the Add Command button, and then click **Add Command**.
- 5. Check the **Permit Unmatched Args** check box, and click **Submit**

# **Shared Profile Components**

Edit

#### **Shell Command Authorization Set**



### **Scenario 3: Privilege for Restricted Access**

In this scenario, users are able to use selective commands.

In the Shell Command Authorization Set area of the Shared Profile Components window, configure these settings:

- 1. In the name field, enter **Restrict\_access** as the name of the command authorization set.
- 2. Click the **Deny** radio button.
- 3. Enter the commands you want to allow on the AAA clients.
  - a. In the field located above the Add Command button, enter the **show** command, and click **Add Command**.




- b. Enter the **configure** command, and click **Add Command**.
- c. Select the **configure** command, and enter **permit terminal** in the field to the right.




- d. Enter the **interface** command, and click **Add Command**.
- e. Select the **interface** command, and enter **permit Ethernet** in the field to the right.




- f. Enter the ethernet command, and click Add Command.
- g. Select the **interface** command, and enter **permit timeout**, **permit bandwidth**, and **permit description** in the field to the right.



h. Enter the bandwidth command, and click Add Command.



i. Enter the timeout command, and click Add Command.



j. Enter the **description** command, and click **Add Command**.

Shared Profile Components				
and Authorization Set				
Restrict_access				
<u></u>				
O Permit O Deny				
Permit Unmatched Args				


4. Click Submit.

# **Associate the Shell Command Authorization Set to User Group**

Refer to Configuring a Shell Command Authorization Set for a User Group section of the User Guide for Cisco Secure Access Control Server 4.1 for more information about how to configure the shell command authorization set configuration for user groups.

# Associate the Shell Command Authorization Set (ReadWrite Access) to User Group (Admin Group)


1. In the ACS window, click **Group Setup**, and choose **Admin Group** from the Group drop–down list.



- 2. Click Edit Settings.
- 3. From the Jump To drop-down list, choose **Enable Options**.
- 4. In the Enable Options area, click the **Max Privilege for any AAA client** radio button, and choose **Level 15** from the drop–down list.



- 5. From the Jump To drop-down list, choose **TACACS**+.
- 6. In the TACACS+ Settings area, check the **Shell (exec)** check box, check the **Privilege level** check box, and enter **15** in the Privilege level field.



7. In the Shell Command Authorization Set area, click the **Assign a Shell Command Authorization Set for any network device** radio button, and choose **ReadWriteAccess** from the drop–down list.

Group Setup					
	Jump To TACACS+	V			
	Privilege level				
	Timeout				
Shell Command Authorization Set					
	None				
0	<ul> <li>Assign a Shell Command Authorization Set for any network device</li> </ul>				
	ReadWriteAccess 🔽				
0	Assign a Shell Command Authorization : Group Basis	Set on a per Netwo	ork Device		

8. Click Submit

# Associate the Shell Command Authorization Set (ReadOnly Access) to User Group (Read-Only Group)

1. In the ACS Window, click **Group Setup**, and choose **Read-Only Group** from the Group drop-down list.



- 2. Click Edit Settings.
- 3. From the Jump To drop-down list, choose **Enable Options**.
- 4. In the Enable Options area, click the **Max Privilege for any AAA client** radio button, and choose **Level 1** from the drop–down list.



5. In the TACACS+ Settings area, check the **Shell (exec)** check box, check the **Privilege level** check box, and enter **1** in the Privilege level field.

(	Group Setup						
		Jump To TACACS+	V				
		TACACS+ Settings					
		PPP IP					
		In access control list					
		Out access control list					
		Route					
		Routing	☐ Enabled				
	Note: PPP LCP will be automatically enabled if this service						
		Shell (exec)					
		Access control list					
		Auto command					
		Callback line					
		Callback rotary					
		Idle time					
		No callback verify	☐ Enabled				
		No escape	☐ Enabled				
		No hangup	☐ Enabled				
		Privilege level	1				

6. In the Shell Command Authorization Set area, click the **Assign a Shell Command Authorization Set for any network device** radio button, and choose **ReadOnlyAccess** from the drop–down list.




7. Click Submit

# Associate the Shell Command Authorization Set (Restrict\_access) to User


Refer to Configuring a Shell Command Authorization Set for a User section of the User Guide for Cisco Secure Access Control Server 4.1 for more information about how to configure the shell command authorization set configuration for users.

**Note:** User–level settings override group–level settings in ACS, which means if the user has shell command authorization set in the user–level settings, then it overrides the group–level settings.

1. Click **User Setup > Add/Edit** in order to create a new user named *Admin\_user* to be part of Admin group.



2. From the Group to which the user is assigned drop-down list, choose **Admin Group**.



3. In the Shell Command Authorization Set area, click the **Assign a Shell Command Authorization Set for any network device** radio button, and choose **Restrict\_access** from the drop—down list.

**Note:** In this scenario, this user is part of Admin Group. The *Restrict\_access* shell authorization set is applicable; the *ReadWrite Access* shell authorization set is not applicable.

User Setup				
☐ No callback verify	☐ Enabled			
☐ No escape	☐ Enabled			
☐ No hangup	☐ Enabled			
☐ Privilege level				
☐ Timeout				
Shell Command Author	rization Set			
C None				
C As Group				
<ul> <li>Assign a Shell Command Authorization Set for any network device</li> </ul>				
Restrict_access ▼				
C Assign a Shell Command Authorization Set on a per Network Device Group Basis				

**Note:** In the TACACS+ (Cisco) section of the Interface Configuration area, ensure that the **Shell** (exec) option is selected in the User column.

## **IOS Router Configuration**

In addition to your preset configuration, these commands are required on an IOS router or switch in order to implement command authorization through an ACS server:

```
aaa new-model
aaa authorization config-commands
aaa authorization commands 0 default group tacacs+ local
aaa authorization commands 1 default group tacacs+ local
aaa authorization commands 15 default group tacacs+ local
tacacs-server host 10.1.1.1
tacacs-server key cisco123
```

### **ASA/PIX Configuration**

In addition to your preset configuration, these commands are required on ASA/PIX in order to implement command authorization through an ACS server:

```
aaa-server authserver protocol tacacs+
aaa-server authserver host 10.1.1.1
aaa authorization command authserver
```

#### **NetPro Discussion Forums – Featured Conversations**

Networking Professionals Connection is a forum for networking professionals to share questions, suggestions, and information about networking solutions, products, and technologies. The featured links are some of the most recent conversations available in this technology.

Security: Intrusion Detection [Systems]			
Security: AAA			
Security: General			
Security: Firewalling			

## **Related Information**

- Cisco PIX Firewall Software
- Cisco Secure PIX Firewall Command References
- Security Product Field Notices (including PIX)
- Requests for Comments (RFCs)
- Cisco Secure Control Access Control Server Support Page
- Technical Support & Documentation Cisco Systems

All contents are Copyright © 2006–2007 Cisco Systems, Inc. All rights reserved. Important Notices and Privacy Statement.

Updated: Oct 12, 2007 Document ID: 99361